

## ❑ DEcommission related Commands

CMDs	Comments
<p><b><u>Decommission</u> node</b></p> <p><b>New in 7.1.3</b></p>	<p>To finally remove a <b>BA client</b>. Backup data for node <b>expires</b> according to policy settings unless you explicitly delete the data. AND <b>New in 8.1.7:</b> also <b>RETENTION SET expiration is taken into account</b></p> <p>→ check with: q node &lt;node_name&gt; f=d</p>
<p><b><u>Decommission</u> VM</b></p> <p><b>New in 7.1.3</b></p>	<p>To remove <b>an individual VM</b> within a data center node. The file space that represents the VM is deleted from the server only after its backup data expires. Check with „q fi“ .</p>

```
Decommissioned: Yes
Decommissioned Date: 06/17/2020 21:15:36
```

➤ **Other cmds / functions initiated** by the decommissioning process:

**If node is replicated:**

upd node xx  
replstate=disabled or  
remove replnode xx

- Change from **active** to **inactive** version
- Delete schedule association
- EXPIRE Inventory
- LOCK / UNLOCK (for restore / retrieve) node
- DEL filespace
- REMOVE node (initiated **finally** by **expire inventory** cmd)

## ❑ REcommission related Commands - New in 8.1.10

→ Reset the „Decommissioning“ of a Node or VM

CMDs	Comments
<p><b>Recommission node</b></p> <p>New in 8.1.10</p>	<p>To <b>recommission</b> a TDP or standard BA Client decommissioned by using the <b>DECOMMISSION NODE</b> command.</p> <ul style="list-style-type: none"> <li>• Node is <b>unlocked</b> and data can be backed up again.</li> <li>• Any “<b>inactivated</b>” backup version will <b>keep</b> it’s status.</li> <li>• Node <b>can be decommissioned again</b> if needed.</li> </ul> <p>→ check with <code>q node &lt;node_name&gt; f=d</code></p> <pre>Decommissioned: Decommissioned Date:</pre> <p>→ NO entries</p>
<p><b>Recommission VM</b></p> <p>New in 8.1.10</p>	<p>To <b>recommission</b> an VM which was decommissioned by using the <b>DECOMMISSION VM</b> command</p> <p>→ check with <code>q fi &lt;xy&gt; f=d</code></p>